Distribué par :



Contact : hvssystem@hvssystem.com

Tél : 0326824929 Fax : 0326851908

Siège social : 2 rue René Laennec 51500 Taissy France

www.hvssystem.com



Machines connection service

M2Me_Connect

User guide Document reference : 9017809-01





The M2Me_Connect service is provided by

ETIC TELECOM 13 Chemin du vieux chêne 38240 MEYLAN FRANCE

En cas de difficulté dans la mise en oeuvre du produit, vous pouvez vous adresser à votre revendeur, ou bien contacter notre service support :

> TEL : + 33 4-76-04-20-05 FAX : + 33 4-76-04-20-01 E-mail : hotline@etictelecom.com web : <u>www.etictelecom.com</u>



OVERVIEW

1	DELIV	ERY CONTENT	5
2	M2ME	_CONNECT OVERVIEW	5
	2.1	Functions provided by the M2Me_Connect service	5
	2.2	How to use the M2Me_Connect service	6
	2.3	How it works	6
	2.4	Connection security	7

SOFTWARE INSTALLATION

1	M2ME_SECURE SOFTWARE INSTALLATION	9
2	MICROSOFT.NET FRAMEWORK 2.0 COMPONENT INSTALLATION	11
3	INSTALLING A NEW VERSION OF M2ME_SECURE	12
4	X509 CERTIFICATE INSTALLATION	13

CONFIGURATION

1	« M2ME_CONNECT » CONNECTION CONFIGURATION	15
2	PROXY SERVER	16
3	CERTIFICATE	16
4	MODEM DECLARATION	16

OPERATION

1	LAUN	ICHING M2ME_SECURE	17
2	M2ME_SECURE MAIN PAGE OVERVIEW1		
3	CREATING REMOTE SITES		
	3.1	« General » tab	19
	3.2	« Connection » tab	19
4	SAVI	NG OR RESTORING THE REMOTE SITES DIRECTORY	
5	CON	NECTING THE PC TO A REMOTE SITE USING M2ME_CONNECT	20
	5.1	Step 1 : Connecting the PC to the M2Me_Connect service	20
	5.2	Step 2 : Connecting the PC to a remote site	21
6	CON	NECTING A PC TO A REMOTE SITE THROUGH THE PSTN	23
7	CON	NECTING A PC TO A REMOTE SITE DIRECTLY THROUGH THE INTERNET	24
DIA	GN	OSTIC	

	1	TRACING THE CONNECTION	25
--	---	------------------------	----

APPENDIX 1 : CHECK-LIST



Delivery content

The M2Me_Connect CD includes the following parts :

The M2Me_Secure connection software.

An X509 authentication certificate (.p12 file).

The documentations of the service and also of the various RAS-routers manufactured by ETIC TELECOM.

2 M2Me_Connect Overview

2.1 Functions provided by the M2Me_Connect service

The M2Me_Connect service is specially efficient for remote maintenance of automated systems.

The M2Me_Connect service makes possible to set a secure connection between

- A PC on one hand,
- and an Ethernet or a serial network on the other hand through the Internet.

The M2Me_Connect service makes that connection possible and easy even if the IP addresses are dynamic or private addresses.





Internet direct connection :

If the remote site RAS-router is directly connected to the Internet with a fixed IP address for instance, or at least with a public dynamic IP address, the M2Me_Secure software allows to connect the PC directly to the RAS-router with a TLS secure connection.



PSTN connection :

If the remote RAS-router is not connected but to the telephone network (RAS-M156e), the M2Me_Secure software allows to connect the PC directly to the RAS-router with a PPP connection through the PSTN using the modem of the PC.



- 2.2 How to use the M2Me_Connect service
- The PC must subscribe to the M2Me_Connect service.
- The PC must run either Windows 2000 or XP or VISTA or Seven 32 bits.
- The M2Me_Secure software and the X509 certificate delivered with the software must be installed on the PC.
- The remote machine must be connected to a RAS-router compatible with the M2Me_Connect service.
- Both the PC and the RAS-router must have an access to the Internet and must have the right to set an outgoing TLS VPN connection either over UDP or TCP.
- 2.3 How it works

1 step : VPN connection to the service

The PC on one side, and the RAS on the other side set a VPN to the M2Me_Connect service.

Their certificate are checked by the M2Me_Connect server which manages the certificate data base.

2nd step : End to end connection from the PC to the RAS

The PC establishes an end to end safe connection with the RAS.

That connection can only be established

• If the product key of the RAS has been stored in the M2Me_Secure machine list,

And

• If the login and password of the remote PC user has been stored in the User list of the RAS.

<u>Once connected, an IP address of the machine remote network is automatically assigned to the PC.</u> The PC can exchange data with each device of the remote network as if it was directly connected to it.

It is only limited by the firewall of the RAS.



2.4 Connection security

The M2Me_Connect service provides a high level of security.

Subscriber restricted group :

A PC can connect to the M2Me_Connect service only if its X509 certificate has been stored in the M2Me_Connect server.

PC & machine authentication :

The PC can establish an end to end connection with a RAS only if the RAS product key has been stored in the M2Me_Secure.

A PC cannot establish a connection with a RAS if it does not know its product key.

Remote user authentication :

The connection from the PC to the RAS can be set only if the remote user Id and password have been stored in the RAS user list.

IP domain limitation :

The domain to which the remote user can connect is limited by the firewall included in the RAS. According to the remote user Identity, it will be able to communicate with such machine and not with such other one.

End to end Encryption :

The data which are transmitted are encrypted by the PC on one hand and by the RAS on the other hand.

In that way, they cannot be spied neither from the Internet nor inside the M2Me_Service server.



M2Me_Secure software installation

- Insert the M2ME_Secure software CD.
- Browse the CD; choose the English folder.
- Click the Setup icon.

The installation windows is displayed.

Click "Next".



- Select the installation location and click "Next".
- Confirm; the installation will start.

🛱 M2Me	
Select Installation Folder	
The installer will install M2Me to the following folder.	
To install in this folder, click "Next". To install to a different folder, enter it be	elow or click "Browse".
<u>F</u> older:	
C:\Program Files\Etic Telecom\M2Me\	Browse
	Disk Cost
Install M2Me for yourself, or for anyone who uses this computer:	
€ Everyone	
⊂ Just <u>m</u> e	
Cancel < <u>B</u> ack	Next >

SOFTWARE INSTALLATION

During the Installation process, a Warning window may be displayed indicating that some components are not certified by Microsoft.

• Click "Continue" each time the Warning window is displayed.



• Once the installation is finished, click "Close ".

The M2Me icon is displayed on the desktop.

Two networks connections named "TAPWIN32 V9" and "TAPWIN32 V9 #2" have been created.



2 Microsoft.net framework 2.0 component installation

If the Microsoft.net framework 2.0 component is not available inside the PC, the installation process is immediately interrupted.

The license window is displayed.

• Click « Accept ».

The microsoft component is automatically downloaded from the Internet.

linstallatio	on de M2Me		Þ
Pour les compo	osants suivants :		
.NET Frame	work 2.0		_
Lisez le contral la suite du con	t de licence suivant. trat.	Appuyez sur PG. SUIV. pour consi	ulter
TERMES DU MICROSOFT MICROSOFT EXPLOITATIO MICROSOFT	CONTRAT DE LICE NET FRAMEWORK IN MICROSOFT WI WINDOWS INSTAL WINDOWS INSTAL	NCE D'UN COMPLÉMENT (2.0 POUR LE SYSTEME D' NDOWS LER 2.0 LER 3.1	^
Microsoft Corp ses filiales) vo détenez une li	poration (ou en foncti us accorde une licer cence d'utilisation d	ion du lieu où vous vivez, l'une de nee pour ce Complément. Si vous u logiciel Microsoft Windows (le «	×
Afficher	le CLUF pour l'imprin	ner	
Acceptez-vo	ous les termes du	présent contrat de licence ?	
Si vous choisis accepter ce co	sez Ne pas accepte ontrat pour effectuer	r, l'installation se terminera. Vous de l'installation.	evez
	*******	Manage and an and a second sec	

If the PC is not connected to the Internet, or if the download process has not been successful, the framework2.0 component is available in the « M2Me_Connect » CD.

- Select the « M2Me_Connect » CD.
- Click the « dotnetfx» folder, and then the « dotnetfx.exe» icon.
- Once finished, start the PC again and click the Setup icon of the M2Me CD to start the installation of the M2Me_Secure.



3 Installing a new version of M2Me_Secure

Before upgrading the M2Me_Secure software, it is necessary to carry-out the following steps :

1step : Save the M2Me_Secure Remote sites directory

- Click "Menu" and then "Options".
- Select the "Maintenance" tab.
- Click "Save" and assign a name to the file.

2nd step : Uninstall the existing M2Me_Secure version

• Uninstall M2Me_Secure using the Windows Configuration panel.

3rd step : Install the new M2Me_Secure version

See above.

4th step : Check the Remote site previous directory is correctly installed

• Launch M2Me_Secure and check your remote sites directory is correctly displayed.

If it is not,

- Click "Menu" and then "Options".
- Select the "Maintenance" tab.
- Click "Restore" and restore the file.



4 X509 certificate installation

The PC authenticates to the service with an X509 certificate. It must be installed in the PC.

That certificate is provided by ETIC Telecom. It is stored in the M2Me_Connect CD.

• Launch M2Me_Secure.

The "Certificate Warning window" is displayed.

• Click the « Install now » button.

The "Certificate window" is displayed.

- Select the « Certificate » folder inside the M2Me_Connect CD .
- Select the file « xxxxxxxx-xxxx-xxxxxxxx-xxxxxxxxxxx.p12 ».
- Enter the password « etic ».
- Click « Install » and then « Close ».

	M2Me - Certificate
rt	You have not yet installed a certificat. This one is mandatory in order to connect to M2Me_Connect service.
	Install now Later

M2Me - Certifica	ite installation 🛛 🔀
	The certificate to install is a p12 type file. It is password protected.
File location :	XXX-8XX7-edbXX421XXXa.p12 Browse
Password :	
	Install Cancel

Remark :

Store the CD properly, because it contains the certificate. It will be necessary If you need to install the certificate again, after crashing a hard disk for instance.

If you have lost the certificate, call our holine.





- Launch M2Me_Secure.
- Enter the user name and the password.

Attention : That user name and password are checked by the RAS ; they must be stored in the user list of the RAS otherwise the connection will not be accepted.

M2Me - User identification				
Enter your username and password used when connecting to a remote site.				
Username :	admin			
Password :	****			
Confirm password :	жини			
Save this username and password				
ОК				

To setup the connection to the M2Me_Connect service, click "Menu" and then "Option".

The Configuration window is displayed. It shows five tabs.

The "M2Me" tab allows to set-up the parameters of the VPN connection to the M2Me_Connect service.

The « Proxy » tab allows to register the parameters of the Proxy server eventually installed on the local network.

The «Certificate» tab allows to display the stored certificate characteristics or to store a new certificate.

The « Modem » tab allows to declare a PSTN modem if direct PSTN connection to a remote site is required.

The « Diagnostic » tab allows to trace the connection if needed.

M2Me Connect Pr	oxy Certificate Moden	n Maintenance Diagnostic
General		
📃 Sign in	to M2Me_Connect servic	ce at startup
Port : 500 111 500	000 34 A 00	Protocol : UDP 🗸
00		Lietault parameters
		Default parameters
		Derault parameters
Modify adva	nced parameters	
Modify adva	nced parameters	
Modify adva	nced parameters eticnet1.com	
Modify adva	nced parameters eticnet1.com	
Modify adva Advanced Server 1 : Server 2 : Server 3 :	eticnet1.com	
Advanced Server 1 : Server 2 : Server 3 : Login :	nced parameters eticnet1.com admin	
Modify adva Advanced Server 1 : Server 2 : Server 3 : Login : Password :	nced parameters eticnet1.com admin admin	Default parameters

I « M2Me_Connect » connection configuration

• Select the M2Me_Connect tab. And set the parameters as follows :

"Sign in to M2Me_Connect service at startup" check box

Tick that checkbox if you wish that the PC connects automatically to the M2Me_Connect service as soon as the software is launched.

« Protocol » and "port number" parameter :

The VPN connection from the PC to the service is a TLS connection. It can be encapsulated either inside the TCP or the UDP protocol . Select the protocol UDP or TCP and the port number : 80, 443, 1194, 5000, 50000 or enter a port number between 50000 and 51000.

«Modifiy advanced parameters » checkbox:

Select that checkbox only on demand of our client department.



A proxy is an IP server connected to an IP network made to control the connections to the Internet.

That tab allows to enter the characteristics of the proxy server.

<u>« Use a proxy server" checkbox :</u> Select the checkbox.

« HTTP » or « SOCKS » parameters :

Select one option or the other.

<u>« Address » & « Port » parameters :</u> Enter the IP address of the proxy server and the port number to use to connect to the proxy server.

«Login» & «password» parameters :

Enter the login and password of the proxy server.

Attention : If a proxy server filters the connection to the Internet, the TCP protocol and the port number 443 will be used to connect to the M2Me_Connect service.

3 Certificate

If the certificate has not been installed previously, click the « Install a certificate » button and install the certificate.

4 Modem declaration

The M2Me_Secure software can also be used to connect the PC to a RAS -M156e (this is the reference of a product made for PSTN) directly through the PSTN.

If you wish to be able to use the modem of the PC and the PSTN to connect directly the PC to particular remote sites,

• Click the "Configure" button and select one modem among the ones which are available.



οκ

User identification

Save this username and password

00

Username Password

Confirm password :

Enter your username and password used when connecting to a remote site.

admin

1 Launching M2Me_Secure

Launch M2Me_Secure.

Enter the user name and the password.

Attention : That user name and password are checked by the RAS ; they must be stored in the user list of the RAS otherwise the connection will not be accepted.

2 M2Me_Secure main page overview

The main page of M2Me_Secure is displayed. It is divided in 4 parts :

At the top, a control bar to configure the M2Me_Secure and connect the PC to a remote site.

On the left, the remote site directory; it is a tree of folders. Each folder is a group of remote sites.

On the right, the list of the remote sites. It is the content of the selected folder.

On the bottom, a message bar to display the PC connection status.



A green C character is displayed in front of each remote site when it is connected to the M2Me_Connect Service.

A grey C character with a red cross is displayed in front of each site able to connect to the service but not connected at the moment.

When no sign is displayed in front of a remote site, it means, it is not able to connect to the M2Me_Connect service. This situation occurs if a remote site is configured to be accessed only through the PSTN or directly with a public IP address and not through the M2Me_Connect service.



OPERATION

Remark :

When the M2Me_Secure is launched for the first time, a certain number of folders containing remote sites have already been registered. All that remote sites are located in our technical platform. They can be used for test purpose.

3 Creating remote sites

The M2Me_Secure main page displays a tree of folders. Each folder is a group of remote sites.

To connect a PC to a remote site, the remote site must be registered in the Remote sites directory.

To create a group (a folder),

- Select the location of the directory where the group must be created.
- Click the "Menu" icon and then "New group".
- Assign a label to the folder.

To create a site,

- Select the location where the site must be created in the directory.
- Click the "Menu" icon and then "New site".



The "site properties" window is displayed; it includes three tabs :

« General », « Connection » and « Advanced ».

M2Me - Properties	of Spain laser machine 3695	
General Connection	Advanced	
Site name :	Spain laser machine 3695	
Account		
💽 Use the u	sername and password of the session	
🔿 Use a par	rticular username and password	
Userr	name :]
Passv	word :	
Confir	rm password :	
Info :		
	OK Car	ncel



3.1 « General » tab

<u>« site name» parameter :</u>

Assign a label to the remote site.

« Use the username and password of the session» checkbox

If that checkbox is selected, the login and password entered just when lauching the M2Me_Secure software are transmitted to the RAS when the PC connects. Selecting that checkbox is advised.

3.2 « Connection » tab

Select the « The site can be reached through Internet » checkbox.

Select the « The site can be reached through M2Me » checkbox.

« Product key » Parameter :

Enter the « product key » code which identifies the remote RAS-router.

The "product key" can be copied from the menu ABOUT of the RAS-router/

4 Saving or restoring the remote sites directory

We advise to save the remote sites directory, especially if it contains a great number of sites.

In case of hard disk crash it might take a long time to acquire again each RAS-router and product key and to re-build the remote sites directory.

To save the remote sites directory :

- Click "Menu" and then "Options".
- Select the "Maintenance" tab.
- Click "Save" and assign a name to the file.

To restore the remote sites directory file :

- Click "Menu" and then "Options".
- Select the "Maintenance" tab.
- Click "Restore", select the file and restore it.



5 Connecting the PC to a remote site using M2Me_Connect

The PC can be connected to a remote site through the M2Me_Connect service only if a green **C** character is displayed in front of that remote site label.

The connection is carried-out in two steps :

1st step : Connecting the PC to the M2Me_Connect service.

2nd step : Connecting the PC to the remote site.

5.1 Step 1 : Connecting the PC to the M2Me_Connect service

If the « Sign-in to M2Me_Connect service at start up» checkbox has been selected, the PC connects automatically to the service as soon as the software has been launched.

• Otherwise, to connect the PC to the service, click « Menu » and then « Sign-in to M2Me_Connect service ».

During the connection, , the message « Authentication on M2Me_Connect service » is displayed at the bottom of the screen.

When the PC is connected to the service M2Me_Connect,

the green character ${f e}$ is displayed at the bottom of the screen, and

a green character **e** is displayed in front of each remote site connected to the service.





5.2 Step 2 : Connecting the PC to a remote site

The PC can connect to a remote site through the M2Me service, if a green **C** character is displayed in front of the remote site label.

- Select the remote site.
- Click the Internet connection button.



The user ID window is displayed.

• Click OK to confirm or enter a new login and password.

Attention : The login and password must be stored in the RAS; otherwise the connection will be rejected.



When the PC is connected to the RAS, a safety message is displayed.

If all precautions have been taken to act remotely without danger, click OK.



A figurine is displayed in front of the line of the remote site to which the PC is connected.

An end to end VPN is established between the PC and the RAS-router of the remote site.

The PC is now virtually connected to any authorised device of the remote network.

• Once all remote operations have been completed, click the Disconnect button of the control bar.

The end to end secure connection from the PC to he RAS is cleared but the PC will remain connected to the M2Me_Connect service.





6 Connecting a PC to a remote site through the PSTN

If some sites are not connected to the Internet, the M2Me_Secure allows to connect the PC to such sites using its V90 modem and the telephone network.

To Crate a remote site reachable through the PSTN,

 Create a site, or select a remote site already created, right click and select the "Site properties " menu.

The "Properties" window is displayed.

- Select the "Connection" tab and then the "This site is reachable through the PSTN" checkbox.
- Enter the telephone number of the remote site.
- Click OK.

The site is now ready to be reached through the PSTN.

To connect the PC to that site,

• select the site and click the PSTN connection button.





7 Connecting a PC to a remote site directly through the Internet

For any reason, it may be useful to connect to a remote site directly through the Internet without using the M2Me_Connect service.

To do so, the properties the remote site must be configured properly :

 Create a site, or select a remote site already created, right click and select the "Site properties" menu.

The "Properties" window is displayed.

- Select the "Connection" tab and then the "This site is reachable through the Internet" checkbox.
- Check the "This site is viewable through the M2Me_Connect service" checkbox is not selected.
- Enter the Product key of the RAS.
- Enter the host name or the IP address of the RAS.
- Click OK.

The site is now ready to be reached through the Internet with ab IP address or a DNS name or a DynDNS name.

To connect the PC to that site,

• select the site and click the Internet connection button.





1

Tracing the connection

If the PC does not connect to the M2Me_Service

- Click « Menu » and then « Options ». The Options window is displayed.
- Select the "Trace the connection to M2Me_Connect service" checkbox and the "Trace the connection to the RAS" checkbox. The Monitor window is displayed.
- Connect the PC to the M2Me_Connect service.
- Copy the messages from the Monitor window to a word processing software and contact the hotline.



The table hereafter is the list of the Informations which are necessary to configure the connection from the PC to the M2Me_Connect service.

Transport protocol (TCP or UDP)	
Attention TCP & the port nr 443 is the only solution if a proxy server filters the connection to the Internet.	
TLS port Nr UDP : 1194 – 5000 – 50000 to 51000 TCP : Idem + 80 & 443	
Proxy server IP address	
Type of the Proxy Server (HTTP or SOCKS5)	
Proxy Server Login	
Proxy Server password	



ETIC TELECOM 13, Chemin du Vieux Chêne 38240 Meylan - France

Tel : 33 4 76 04 20 00 Fax : 33 4 76 04 20 01 E-mail : contact@etictelecom.com

Web : www.etictelecom.com



2 rue René Laennec 51500 Taissy France Fax: 03 26 85 19 08, Tel : 03 26 82 49 29

Email : hvssystem@hvssystem.com Site web : www.hvssystem.com